

OVERALL STRUCTURE

NAVBAR:

- Contains HOME and FUNCTIONS buttons
- Note: Among FUNCTIONS' screens, only need to work on FUNCTION-A screen for now.

WORKSPACE:


- User moves/adjusts shapes here
- It has an invisible grid (so shape movement/adjustment should follow grid resolution).
- User can zoom in/out

SIDEBAR:

- User can input/view details here

KEYBOARD:

- For user to input numbers



Function-A screen

When Function-A screen first opened

- Operation shape shown (let's call it `CURRENT_SHAPE`) should be a duplicate/copy of the last Operation shape that was created by User on any Function screen in the app.

`CURRENT_SHAPE`'s parameters' values are shown in sidebar.

`CURRENT_SHAPE` can be adjusted using the four adjustment buttons around it.

In case User wants to replace the `CURRENT_SHAPE` with another, then...

--OPTION 1) User can press Settings button and select a different type of shape (here, a Circle).

--OPTION 2) If user press-holds another existing shape's outline seen on screen...

- Then a duplicate of that other shape becomes `CURRENT_SHAPE` (i.e., all the parameters' values get imported to the new one)

HOME



FUNCTION-A



FUNCTION-B



FUNCTION-C



FUNCTION-D



FUNCTION-E



FUNCTION-F



FUNCTION-G




FUNCTION-H



FUNCTION-I



FUNCTION-J



FUNCTION-A

X POSITION

93.7

Y POSITION

93.7

Z POSITION

93.7

CUT STYLE



INSIDE



OUTSIDE



INFILL

DIAMETER

93.7

DEPTH

93.7



EXPORT



ADD TO
SEQUENCE



1

2

3

4

5

6

7

8

9

0

.

+

-





Function-A screen

At any time, User can drag the outline of CURRENT_SHAPE to move it anywhere.

To move-snap to another shape:

- User double-presses some place on CURRENT_SHAPE's outline.
- Then the nearby key-point of CURRENT_SHAPE gets highlighted in Grey.
- Also, key-points of all other shapes are shown in Orange.
- When User presses another shape's key-point, then CURRENT_SHAPE selected key-point is moved to the other shape's selected key-point (so CURRENT_SHAPE is moved).






Function-A screen

To resize CURRENT_SHAPE:

User holds the RESIZE button and pulls in any direction.



Function-A screen

To rotate CURRENT_SHAPE:

User holds the ROTATION button and drags to any angle around the shape.

HOME



FUNCTION-A



FUNCTION-B



FUNCTION-C



FUNCTION-D



FUNCTION-E



FUNCTION-F



FUNCTION-G




FUNCTION-H



FUNCTION-I



FUNCTION-J



FUNCTION-A

X POSITION

93.7

Y POSITION

93.7

Z POSITION

93.7

CUT STYLE



INSIDE



OUTSIDE



INFILL

LENGTH

93.7

WIDTH

93.7



EXPORT



ADD TO
SEQUENCE



1

2

3

4

5

6

7

8

9

0

.

+

-



Function-A screen

To create a chamfered/rounded-corner on CURRENT_SHAPE:

On specific points:

- User presses the CORNER button
- User presses one or more points, and then does the usual adjustment.

For all points together:

- User holds the CORNER button and pulls either inward (for chamfer) or outward (for rounded corner) from the shape.

HOME



FUNCTION-A



FUNCTION-B



FUNCTION-C



FUNCTION-D



FUNCTION-E



FUNCTION-F



FUNCTION-G




FUNCTION-H



FUNCTION-I



FUNCTION-J



FUNCTION-A

X POSITION

93.7

Y POSITION

93.7

Z POSITION

93.7

CUT STYLE



INSIDE



OUTSIDE



INFILL

LENGTH

93.7

WIDTH

93.7



EXPORT



ADD TO
SEQUENCE



1

2

3

4

5

6

7

8

9

0

.

+


-



Function-A screen

To change Depth parameter (only numeric value, no shape change) of CURRENT_SHAPE:


- User presses the DEPTH button
- Workspace shows vertical slider on left, which User can adjust



HOME screen

Sidebar: Sequence shows collection of all Operations created by user (When user presses “Export” or “Add to Sequence” buttons in FUNCTION-A screen’s sidebar).

—
NEXT: If user does a press-hold at any point on the Workspace in HOME screen, then...



HOME screen


Then Workspace shows red marker where User did a press-hold.

Sidebar shows coordinates of that point.

—
NEXT-A: If user releases the hold now, then User has **chosen one point**. User can then press SCAN POINT button.

Or

NEXT-B: If user had continued the hold by dragging to another point, then User has **chosen two points**. [see next page]



HOME screen

If User has chosen two points (Yellow and Red markers), then Workspace shows a dashed box between the user's chosen points.

Sidebar shows values for that box, and button name is updated to SCAN AREA.

—
NEXT: If user presses SCAN AREA button, then...

HOME



FUNCTION-A



FUNCTION-B



FUNCTION-C



FUNCTION-D



FUNCTION-E



FUNCTION-F



FUNCTION-G




FUNCTION-H



FUNCTION-I



FUNCTION-J



SCAN

Completed successfully.



BACK TO HOME



CLEAR SCAN



1

2

3

4

5

6

7

8

9

0

.

+

-



HOME screen

...Then Workspace shows an image inside the box.

Sidebar says "Completed successfully".